

Copyright (c) 2008-2010, Fiorano Software Pte. Ltd. And affiliates.

All rights reserved.

This software is the confidential and proprietary information of Fiorano Software ("Confidential Information"). You shall not disclose such ("Confidential Information") and shall use it only in accordance with the terms of the license agreement enclosed with this product or entered into with Fiorano.

Contents

FioranoMQ JMX API's	8
----------------------------------	----------

Chapter 1: Loggers	9
---------------------------------	----------

1.1 MBeans related to Logger	9
1.2 Operations of Logger	11
1.2.1 Adding Appenders	11
1.2.2 Adding File Appender	12
1.2.3 Adding Console Appenders	13
1.2.4 Clearing Logs	14
1.2.5 Removing Appenders	14
1.2.6 Listing Appenders	14
1.2.7 Fetching Details of Appenders	14
1.2.8 Fetching Logs	15
1.2.9 LogLevel	16

Chapter 2: JNDI	17
------------------------------	-----------

2.1 Operations of JNDI Services	17
2.1.1 Looking up Administered Objects	17
2.2 Attributes for JNDI	17
2.2.1 AdminObjectFileName	17
2.2.2 AdminObjectBackupFilename	17
2.2.3 AdminObjectDefragFilename	18
2.2.4 Path	18
2.2.5 DefragmentationLowerThreshold	18
2.2.6 DefragmentationUpperThreshold	18
2.2.7 DefragmentationPercentage	18

Chapter 3: Connection Manager	19
--	-----------

3.1 Attributes of Connection Manager	19
3.1.1 NumberOfClientConnections	19
3.2 Operations on Connection Manager	19
3.2.1 Listing Clients	19
3.3 Attributes of Connection Manager Config	19
3.3.1 Default	19
3.3.2 CFNameAppender	20
3.3.3 ReaderCacheDisabled	20

3.3.4 TCPWindowSize	20
3.3.5 HandshakeInWorkerThread	20
3.3.6 MagicTimeout.....	20
3.3.7 Port	21
3.3.8 Protocol.....	21
3.3.9 UseNagle	21
3.3.10 MonitoringRequest	21
3.3.11 MonitoringResponse	21
3.3.12 EnforceJsseAuthentication	22
3.3.13 MaxSocketConnections	22
3.3.14 MaxClientConnectionsCount.....	22
3.3.15 AdminConnection	22
3.3.16 Path.....	23
3.3.17 ServerAddress	23
3.3.18 HandShakingDisabled	23
3.3.19 ManagerClassName	23

Chapter 4: Jmx 24

4.1 Attributes for RMIBasedJMXConnector.....	24
4.1.1 RMIServerPort.....	24
4.2 Attributes for ClientJMXEngine	24
4.2.1 SecurityProtocol	24
4.2.2 Protocol	24
4.2.3 SecurityManagerClass	25
4.2.4 QueueConnectionFactory	25
4.2.5 ServerPort	25
4.2.6 ServerAddress.....	25
4.2.7 Username.....	25
4.2.8 Password.....	26
4.2.9 ConnectQueueName.....	26
4.2.10 RequestQueueName	26
4.2.11 NotifQueueName.....	26
4.2.12 ConnectQueueName	26

Chapter 5: Etc 27

5.1 Job Managers	27
5.1.1 Attributes of TopicDemuxJobManager	27
5.1.2 Attributes of TopicDemuxJobManager Config.....	27
5.1.3 Attributes of PTPWriteJobManager	28
5.1.4 Attributes of PTPWriteJobManager Config	29
5.1.5 Attributes of PTPReadJobManager	29
5.1.6 Attributes of PTPReadJobManager Config.....	30
5.1.7 Attributes of TopicWriteJobManager.....	31

